

Blacknest Data System (BDS) BdsImport Programs – 1.1.8 - 2009-12-10

1. Introduction

The BdsImport programs provide simple command line programs for adding seismic data to the BDS system. The BdsImport programs are clients of the BdsServer and connect through the DataAddAccess API in order to import the requested data.

2. Usage

There are currently 4 import programs developed:

- **bdsImportData:** Imports general seismic sensor data files including: BDRS, GCF.
- **bdsImportBlacknestDatabase:** Imports the old Blacknest Autodrm MySql instrument response database.
- **bdsImportTapeDigitiser:** Imports the TapeDigitiser seismic sensor data files.
- **bdsImportScream:** Daemon to import SCREAM, satellite provided, GCF data files. This is documented in the bdsImportScream document.

The BdsImport programs can be run by any user that has permissions to add data to the BDS system. Generally the BdsImport programs accept the following command line options:

<i>Core Options</i>	
-help	Help on command line parameters
-verbose	Be verbose with comments
-host <hostname>	BDS Server host name
-user <user:password>	The BDS user id and password
-network	Network organisation
-array	The Array the set of data is from, if an array.
-source	The data source (Master)
-format <format>	The input files format
-channels <station1:chan1,station2:chan2>	The list of station/channel names for each data channel
-synchronous	The channels are synchronously sampled
-description <description>	Set the file description
-addWarning <warning>	Add an import warning. Multiple addWarning's can be used
-warnings	Display warnings

BEAM

-dryRun	Perform all data validation tests but don't actually import the data
Validation Options	
-ignoreMissingBlocks	Allow import although validation fails with missing blocks of data. Missing blocks of data are where there is a gap between the end time stamp of one block and the start time stamp of the next block.
-ignoreTimeBackwards	Allow import although validation fails with blocks going backwards in time.
-ignoreFilenameTime	Allow import although validation fails with file name times that do not match block timestamps
-ignoreMetaData	Allow import although validation fails where Database meta-data does not match files meta-data or is not present
-ignoreCorruptions	Fix block corruptions (short/long or otherwise corrupted blocks) by ignoring them (BDRS, WRA-40 and WRA-64)
-ignoreAll	Allow import although validation fails
-reorder	Reorder all data blocks into ascending time order. This is useful with SCREAM supplied data where backfilling of blocks may have occurred.
-deleteDuplicate	Delete any duplicate data blocks. This is useful with SCREAM supplied data where backfilling of blocks may have introduced duplicate blocks.
-numBlocks <numBlocks>	Limit the number of blocks to import (for testing)

The BdsImport program will read the BDS_HOST environment variable at start-up. This variable, if set, defines the default BdsServer host name to contact. The default is "localhost" if this is not set.

The bdsImport programs will first validate the data. The following validations will be performed:

- Generally check for data file corruption. This looks at block headers, makes sure that time stamps are in time order and in range.
- Check that the blocks time-stamps are continuous. If they are not there are missing blocks of data. This error can be ignored.
- Check that the date and time encoded in the file name matches with the time stamps within the data blocks. This error can be ignored.
- Check that the sample rate is correct.
- Check that there is meta-data information in the BDS system for the channels being imported. This error can be ignored.

BEAM

The “-ignore*” flags of the bdsImport programs allows certain validation failures to be allowed. If the validation passes the data is uploaded into the BDS system. If it fails an error message is reported to the user.

There are some example scripts of various Data Imports in /usr/bds/import directory. This code is quite rudimentary.

2.1. BdsImportData

This command line program is able to import all of the existing seismic data files into the BDS system. As well as the options listed above, it accepts a list of file names to import. The contents of these files will be imported into a single BDS seismic sensor data file in the BDS system.

This program can handle any data format supported by the BDS system. It includes: BDRS, GCF and TapeDigitiser data. There is a separate TapeDigitiser data import program that will re-process the TapeDigitisers VELA timecode track and also import more of the meta-information from the TapeDigitiser jobInfo files.

The user will need to supply the file name, the data format and the network, station and channel names for each of the files data channels.

The bdsImportData program first validates the data. The following validations are performed:

- Generally check for data file corruption. This looks at block headers, makes sure that time stamps are in time order and in range.
- If required, (-reorder option), re-order the data blocks into time order.
- Check that the date and time encoded in the file name matches with the time stamps within the data blocks. This error can be ignored.
- Check that blocks time stamps are in sequential order, otherwise issue a Time stamps have gone backwards error.
- Check that the blocks time-stamps are continuous. If they are not there are missing blocks of data. This error can be ignored.
- Check that the sample rate is correct.
- Check that there is meta-data information in the BDS system for the channels being imported. This error can be ignored.

The “-ignore*” flags of the bdsImportData program allows certain validation failures to be allowed. If the validation passes the data is uploaded into the BDS system. If it fails an error message is reported to the user.

If the “-synchronous” option is given, then the channels will be marked as synchronously sampled. When marked as such they can be output in data formats, such as BKNAS, which only support this method of data description.

The user will need to supply the list of file names, the data format and the network, array and list of station/channel names for each of the files data channels.

BEAM

2.2. *BdsImportTapeDigitiser*

This command line program is designed specifically to import the TapeDigitiser analogue sample data files into the BDS system. It is passed the directory path name containing the jobInfo.tdi information file and the data files. If it sees a job info file named “jobInfo.tdim”, it uses this in preference to the “jobInfo.tdi” information file.

The program first pre-processes the TapeDigitiser data files to re-calculate the block timestamps using the latest VELA timecode decoder. Once this is done the complete set of sensor-data and meta-data from the TapeDigitiser files is imported into the BDS system.

The data is always input as synchronously sampled data.

The user will need to supply the directory name where the TapeDigitiser data is stored, the data format, the network, the array and list of station/channel names for each of the files data channels.

2.3. *BdsImportBlacknestDatabase*

On a virgin BDS system the meta data can be imported using a suitable program that can import the data from an existing database. For the existing Blacknest MySQL Instrument Response Database there is the bdsImportBlacknestDatabase program. This will go through the existing Instrument Response Database importing all of the information through the BDS API.

Following initial import either the bdsAdminGui or a user written program can import the meta data using the BDS API.

The BdsImportBlacknestDatabase program accepts the following arguments:

-help	Help on command line parameters
-verbose	Be verbose with comments
-host <hostname>	BDS Server host name
-user <user:password>	The BDS user id and password
-db <host:db:user:pass>	Blacknest IR MySQL database

3. Errors and Warnings

Each of the import programs perform a validation of the data prior to import. If there are any failures the errors are printed on stderr. The import programs have the ability to “fix” certain errors and to ignore certain errors if the appropriate flags (-ignore...) are used. When an import issue is ignored or fixed a warning is issued instead of an error. Normally no warnings are printed on stderr unless the -warnings option is used.

As well as listing the errors and warnings on stderr, the warnings are stored in the BDS import seismic data file. They are listed in the “importWarning*” info fields (The * is a number). You can add to the “importWarning*” fields using the -addWarning flag which is useful to add any information based on pre-processing done to the data files.

The system also add the file pathnames of the imported files to the “importFile*” fields in the BDS seismic data file.

BEAM

The syntax of the errors/warnings is a comma separated list of parameters (with a space after the comma for readability). If the user adds a warning it is useful to follow the same convention to allow programs to parse the error/warning strings easily. The syntax is as follows:

Title, File name, Error number, Error string

When these are output on stderr, they are prepended with either “Error, “ or “Warning, “ as appropriate.

4. Validation Errors

The current Validation Warning/Errors include:

<i>Error/Warning</i>	<i>Description</i>
ErrorValidateReorder	If the -reorder flag is specified then data blocks will be re-ordered into time-stamp order. A warning will be issued which describes the re-ordering performed in the form of an ASCII string. The format of this string is a list of block ranges and the re-ordered position. For example "0-10:30" means blocks 0 through 10 have been moved to position 30.
ErrorValidateDuplicate	If any duplicate blocks are detected (blocks having an identical time span) then this error is issued. The -deleteDuplicate blocks option will delete any duplicate blocks making sure that the blocks are truly identical in data as well as time span.
ErrorValidateMissingBlocks	Each blocks start and end times are compared. If there is a gap in time where there is no data then the Missing Blocks Error is issued.
ErrorValidateTimeBackwards	If a blocks start time is before the previous blocks end time then this error is issued.
ErrorValidateFix	If the -ignoreCorruptions flag is used on the system “fixes” corruptions then this warning is issued for every block that has been fixed.

5. Return Value

The programs will return a status value of 0 if all was Ok. They will return a non zero value on error together with a message output on stderr.

6. Further Information

For further information please look at the BDS system documentation at:

<https://portal.beam.ltd.uk/support/blacknest>.